

Product Release Information: LEB Firmware 03.13.01

Product	LEB
Version Number	03.13.01
Firmware Release Date	August 2023
Customer Support	For more information or support, visit the ENGAGE website.

Attention:

This document contains the **Release Notes** for LEB device firmware version **03.13.01.** This version includes feature updates and improvements made after the LEB firmware 03.11.02 released in February of 2023.

Installation and Update Notes:

Device firmware updates are available through the ENGAGE™ cloud database.

From the ENGAGE web portal, each lock may be independently selected by the site administrator to have the latest firmware downloaded during the next scheduled Wi-Fi connection. Alternatively, the site administrator may connect locally to individual locks with the ENGAGE mobile application to update an LEB with the latest firmware.

Firmware versions that will be installed with this update:

Main Application 03.13.01Reader Application 02.16.00

• BLE Application 02.13.06.327,01.10.03,01-1.7.0

• Wi-Fi Application: 02.15.0.1

NOTE: The **BOLD** item(s) are updated from the previous release

Other system components versions to be used with this release: (or newer)

Gateway
MT20W
Android Application
iOS application
ENGAGE
01.64.04
40.05.00
4.7.665
3.11.0
8.3.0

LEB RELEASE NOTES: LEB Firmware 03.13.01

SES-20230802A



Who should update?

Allegion suggests that customers utilize the latest firmware release to take advantage of the latest functionality, bug fixes, and security enhancements. We strive to provide the best products and service for our customers.

Specifically, any customer interested in any of the following New Features and Recent Changes should update their devices.

New Features:

- Support added for HID® Omnikey® Secure Element
 - Supports HID® R8 and Omnikey® Secure Element (OSE)

Recent Changes:

- General Security Updates
- Wi-Fi Security Updates

NOTE: LEB devices that are programmed with ENGAGE 8.3.0 Firmware 03.13.01 may not be Firmware downgraded to a previous version (03.11.02 and older).

Revision	COMMENTS	DATE
SES20230802A	Release Notes for LEB as part of ENGAGE 8.3.0	08-16-23